Command Reference: SetProperty()


Set a property for the time series processor

Version 11.12.05, 2016-09-18


The SetProperty() command sets the value of a property used by the time series processor. The property will be available to subsequent commands that support using \${Property} notation in parameters, for example to specify filenames more dynamically or use with If() commands. This command should not be confused with the SetTimeSeriesProperty() command, which sets a property on specific time series. The following functionality is provided:

- Set a property to a specified value, where the property can be a Boolean, String, DateTime, Double, or Integer type.
- Set a property to a special value such as empty string that may be difficult to assume from the normal property value.
- Remove an existing property so that it is no longer available to the processor. Care should be taken to understand the implications of removing a property. For example, if the property is used in later commands, then removing will cause the processor to not find the property. It may be more appropriate, for example, to set a string property to an empty string rather than removing.


The following dialog is used to edit this command and illustrates the syntax of the command.



SetProperty() Command Editor for General Set Parameters



SetProperty() Command Editor for Special Value Parameters



SetProperty() Command Editor for Removing a Property

The command syntax is as follows:

SetProperty(Parameter=Value,...)

Command Parameters

Parameter	Description	Default
PropertyName	The property name.	None – must be specified.
PropertyType	The property type, used for validation, one of: • Boolean – a boolean • DateTime – a date/time • Double – a floating point number • Integer – an integer • String – a string DateTime objects can be specified with special syntax to use current time and modifiers on the DateTime. See the SetInputPeriod() command for more information.	None – must be specified as when setting a new property, although is not needed when setting to null or removing.
PropertyValue	The value of the property, adhering to property type constraints. Date/time properties should be specified using standard formats such as "YYYY-MM-DD hh:mm:ss", to an appropriate precision. Special date/time syntax is recognized, as shown in the above figure.	None – must be specified when setting a value. The parameter is not needed when setting special values or removing the property.

Parameter	Description	Default
	Global properties can be used with the	
	\${Property} syntax.	
SetEmpty	If specified as True, the String property will be	The PropertyValue
	set to an empty string.	parameter will be used.
SetNaN	If specified as True, the Double property will	The PropertyValue
	be set to the special "not a number" (NaN)	parameter will be used.
	value.	
SetNull	If specified as True, the property will be set to	The PropertyValue
	null (not specified).	parameter will be used.
RemoveProperty	If specified as True, the property will be	The PropertyValue
	removed and will be unavailable to the	parameter will be used.
	processor. Only user-defined properties can be	
	removed (not important internal properties).	

A sample commands file is as follows:

SetProperty(PropertyName="Scenario",PropertyType=String,PropertyValue="Likely")

TSTool Documentation

This page is intentionally blank.