## Command Reference: SetProperty()


Set a property for the time series processor

Version 12.00.00, 2017-03-25

The SetProperty() command sets the value of a property used by the time series processor. The property will be available to subsequent commands that support using \${Property} notation in parameters, for example to specify filenames more dynamically or use with If() commands. This command should not be confused with the SetTimeSeriesProperty() command, which sets a property on specific time series. The following functionality is provided:


- Set a property to a specified value, where the property can be a Boolean, String, DateTime, Double, or Integer type.
- Set a property to a special value such as empty string or other special values.
- Remove an existing property so that it is no longer available to the processor. Care should be taken to understand the implications of removing a property. For example, if the property is used in later commands, then removing will cause the processor to not find the property. It may be more appropriate, for example, to set a string property to an empty string rather than removing.
- Set a property by modifying a previous global property using basic manipulations.

The following dialog is used to edit this command and illustrates the syntax of the command.




SetProperty() Command Editor for General Set Parameters

SetProperty




## **SetProperty() Command Editor for Special Value Parameters**

SetProperty\_Special




SetProperty() Command Editor for Removing a Property

The following illustrates how to perform a math operation on a property. In this case, a new property name can be assigned (or existing name reused) in the PropertyName parameter. The PropertyValue parameter must specify the name of an existing property using \${Property} notation. This causes the old value to be retrieved and then the math operation is performed. A common operation would be to increment a property's value in a For() loop.



**SetProperty() Command Editor for Performing Math showing Main Property Parameters** 



SetProperty() Command Editor for Performing Math showing Math Input

The command syntax is as follows:

SetProperty(Parameter=Value,...)

## **Command Parameters**

Parameter	Description	Default
PropertyName	The property name.	None – must be specified.
PropertyType	The property type, used for validation, one of:	None – must be specified
	• Boolean - a boolean	as when setting a new
	• DateTime - a date/time	property, although is not
	• Double – a floating point number	needed when setting to
	• Integer - an integer	null or removing.
	• String – a string	
	DateTime objects can be specified with special	
	syntax to use current time and modifiers on the	
	DateTime. See the SetInputPeriod()	
	command for more information.	
PropertyValue	The value of the property, adhering to property	None – must be specified
	type constraints. Date/time properties should be	when setting a value. The
	specified using standard formats such as	parameter is not needed
	"YYYY-MM-DD hh:mm:ss", to an appropriate	when setting special
	precision. Special date/time syntax is	values or removing the
	recognized, as shown in the above figure.	property.
	Global properties can be used with the	
SetEmpty	\${Property} syntax.	The December 1/2 live
Secumpey	If specified as True, the String property will be set to an empty string.	The PropertyValue parameter will be used.
SetNaN	If specified as True, the Double property will	The PropertyValue
o civar	be set to the special "not a number" (NaN)	parameter will be used.
	value.	parameter win be used.
SetNull	If specified as True, the property will be set to	The PropertyValue
	null (not specified).	parameter will be used.
RemoveProperty	If specified as True, the property will be	The PropertyValue
	removed and will be unavailable to the	parameter will be used.
	processor. Only user-defined properties can be	
	removed (not important internal properties).	
Add	Value to add to the property value:	No addition.
	<ul> <li>Double or Integer property value will be</li> </ul>	
	incremented by Add.	
	<ul> <li>String property value will have Add</li> </ul>	
	appended.	
	• DateTime property value will be shifted	
	forward in time by Add (e.g., Add=1Day).	
Subtract	Value to subtract from the property value:	No subtraction.
	Double or Integer property value will be	
	decremented by Add.	
	String property value will have Add	
	remove for all occurrences.	

Parameter	Description	Default
	DateTime property value will be shifted	
	back in time by Add (e.g., Add=1Day).	
Multiply	Value to multiply the property value:	No multiplication.
	• Double or Integer property value will be	
	multiplied by Add.	
Divide	Value to divide the property value:	No division.
	• Double or Integer property value will be	
	divided by Add. Dividing by zero will set	
	the result to NaN for Double and null for	
	Integer.	

A sample command file is as follows:

SetProperty(PropertyName="Scenario",PropertyType=String,PropertyValue="Likely")

SetProperty() Cor	nmand
-------------------	-------

TSTool Documentation

This page is intentionally blank.