Command Reference: WritePropertiesToFile()

Write one or more time series processor properties to a file

/ersion 11.02.03, 2015-05-27

The WritePropertiesToFile() command writes the value of one or more time series processor properties to a file (this command replaces the older WriteProperty() command, which is being phased out). The ReadPropertiesFromFile() command can be used to read properties from a file. Processor properties include global defaults such as InputStart, InputEnd, OutputStart, OutputEnd, OutputYearType, WorkingDir, and also user-defined properties set with SetProperty() and other commands. Internally, properties have a name and a value, which is of a certain type (Boolean, string, integer, date/time, etc.). Examples of using the command include:


- creating tests to verify that properties are being set
- passing information from TSTool to another program, such as a Python script
- storing persistent information for later use, such as the date/time that data were last downloaded from a web service

A number of property formats are supported as listed in the following table.

Property File Formats

Format	Description	
NameValue	Simple format, all properties handled as text:	
	PropertyName=PropertyValue	
	PropertyName="Property value, quoted if necessary"	
NameTypeValue	Same as NameValue format, with non-primitive objects treated as simple	
	constructors:	
	PropertyName=PropertyValue	
	DateTimeProperty=DateTime("2010-10-01 12:30")	
NameTypeValue	ypeValue Similar to the NameTypeValue format, however, objects are represented	
Python	using "Pythonic" notation, to allow the file to be used directly by Python	
	scripts:	
	PropertyName="PropertyValue"	
	DateTimeProperty=DateTime(2010,10,1,12,30)	

The following dialog is used to edit this command and illustrates the syntax of the command.



WritePropertiesToFile() Command Editor

WritePropertiesToFile

The command syntax is as follows:

WritePropertiesToFile(Parameter=Value,...)

Command Parameters

Parameter	Description	Default
OutputFile	The property file to write, as an absolute path or	None – must be
	relative to the command file.	specified.
IncludeProperties	The names of properties to write, separated by	If not specified, all
	commas. The * wildcard can be used to indicate	processor properties
	multiple properties.	will be written.
WriteMode	Indicates how the file should be written:	Overwrite
	 Append – append the properties to the file without checking for matches (create the file 	
	if it does not exist)	
	• Overwrite – overwrite the properties file	
	• Update – update the properties in the file by	
	first checking for matching property names	
	(which will be updated) and then appending	
	unmatched properties (not yet implemented)	
FileFormat	Format of the properties file (see descriptions in	NameValue
	the above Property File Formats table):	
	• NameValue	
	• NameTypeValue	
	NameTypeValuePython	
SortOrder	The order to sort properties:	None – order depends
	• Ascending	on order in processor.
	• Descending	
	• None	