Command Reference: WritePropertiesToFile()

Write one or more time series processor properties to a file

Version 11.02.00, 2015-05-06

The WritePropertiesToFile() command writes the value of one or more time series processor properties to a file (this command replaces the older WriteProperty() command, which is being phased out). The ReadPropertiesFromFile() command can be used to read properties from a file. Processor properties include global defaults such as InputStart, InputEnd, OutputStart, OutputEnd, OutputYearType, WorkingDir, and also user-defined properties set with SetProperty() and other commands. Internally, properties have a name and a value, which is of a certain type (Boolean, string, integer, date/time, etc.). Examples of using the command include:


- creating tests to verify that properties are being set
- passing information from TSTool to another program, such as a Python script
- storing persistent information for later use, such as the date/time that data were last downloaded from a web service

A number of property formats are supported as listed in the following table.

Property File Formats

Format	Description		
NameValue	Simple format, all properties handled as text:		
	PropertyName=PropertyValue		
	PropertyName="Property value, quoted if necessary"		
NameTypeValue	Same as NameValue format, with non-primitive objects treated as simple constructors:		
	PropertyName=PropertyValue		
	DateTimeProperty=DateTime("2010-10-01 12:30")		
NameTypeValue	Similar to the NameTypeValue format, however, objects are represented		
Python	using "Pythonic" notation, to allow the file to be used directly by Python		
	scripts:		
	PropertyName="PropertyValue"		
	DateTimeProperty=DateTime(2010,10,1,12,30)		

The following dialog is used to edit this command and illustrates the syntax of the command.



WritePropertiesToFile() Command Editor

WritePropertiesToFile

The command syntax is as follows:

WritePropertiesToFile(Parameter=Value,...)

Command Parameters

Parameter	Description	Default
OutputFile	The property file to write, as an absolute path or relative to the command file.	None – must be specified.
IncludeProperty	The names of properties to write, separated by commas. The * wildcard can be used to indicate multiple properties.	If not specified, all processor properties will be written.
WriteMode	 Indicates how the file should be written: Append – append the properties to the file without checking for matches (create the file if it does not exist) Overwrite – overwrite the properties file Update – update the properties in the file by first checking for matching property names (which will be updated) and then appending unmatched properties (not yet implemented) 	Overwrite
FileFormat	Format of the properties file (see descriptions in the above Property File Formats table): NameValue NameTypeValue NameTypeValuePython	NameValue
SortOrder	The order to sort properties: Ascending Descending None	None – order depends on order in processor.