Command Reference: ReadNwsCard()

Read all time series from an National Weather Service CARD file


/ersion 10.00.00, 2011-03-29

The ReadNwsCard() command reads all the time series in a National Weather Service River Forecast System CARD file (see the **NWSCard Input Type Appendix**). This command can be used to read the following formats:

- Single time series format.
- Ensemble format file, such as generated by the National Weather Service ESPADP software. Each trace will be identified using the historical year for the start of the trace (as the TSID sequence number), and will be available as a time series for other commands.

The full time series identifier for each time series is set using location = station identifier, data source = blank, data type = data type, and data interval = data interval from file header (see also the Read24HourAsDay parameter below).


The following dialog is used to edit the command and illustrates the syntax for the command when reading a single time series.



ReadNwsCard() Command Editor

ReadNwsCard_SingleAlias

The following dialog illustrates reading an ensemble file, assigning the alias to Location-DataType-Interval-TraceNumber.



ReadNwsCard() Command Editor

The command syntax is as follows:

ReadNwsCard(Parameter=Value,...)

The following older command syntax is updated to the above syntax when a command file is read:

TS Alias = ReadNwsCard(Parameter=Value,...)

Command Parameters

Parameter	Description	Default
InputFile	The name of the NWS Card input file to read, surrounded	None – must be
	by double quotes to protect spaces and other special	specified.
	characters.	
Alias	The alias to assign to the time series, as a literal string or	None – must be
	using the special formatting characters listed by the	specified.
	command editor. The alias is a short identifier used by	
	other commands to locate time series for processing, as	
	an alternative to the time series identifier (TSID).	
EnsembleID	Specify when reading an ensemble file to cause an	Do not create an
	ensemble object to be created, which can be referenced	ensemble object.
	by other commands.	
EnsembleName	The ensemble name corresponding to EnsembleID.	None.
NewUnits	The units to convert to after the read.	Do not convert
		the units.
Read24HourAsDay	If True, read 24Hour time series as if the data were	False – read as
	Day interval. Because NWS Card format uses hours 1 to	hourly and shift
	24, treating as 24Hour results in values being saved at	data at hour 24
	hour zero of the next day. Reading as Day interval	to zero of the
	causes the values to be stored without the shift.	next day.
InputStart	Not used with ensembles. The start of the period to read	Use the global
	– specify if the read period should be different from the	input period or if
	global query period. If Read24HourAsDay=True,	not specified
	specify the period using either hour 24 of the start day, or	read all the data
	hour 0 of the next day. This parameter must be specified	in the file.
	to hour precision with hour's aligning with the file's data.	
InputEnd	Not used with ensembles. The end of the period to read	Use the global
	– specify if the read period should be different from the	input period or if
	global query period. If Read24HourAsDay=True,	not specified
	specify the period using either hour 24 of the start day, or	read all the data
	hour 0 of the next day. This parameter must be specified	in the file.
	to hour precision	

The following command file reads a card file containing one time series, reading 24Hour data as Day:

```
ReadNwsCard(Alias="03567500",InputFile="Data\03567500.CARD",
InputStart="1960-01-01 24",InputEnd="2005-12-31 24",
Read24HourAsDay=True)
```

The following example command reads an ensemble file, converts the data (from CFS) to CMS, and reads 24Hour data as Day:

ReadNwsCard()	Command
---------------	---------

TSTool Documentation

This page is intentionally blank.